


MIXFOOD AMBI NATURE – OPERATION MANUAL



Studio Corbach – Oktober 2024

<https://www.mixfoodmusic.com/ambi-nature-ambiance-generator/>


<https://www.mixfoodmusic.com/contact/>

Description

283 Super High Quality nature samples, looped and solo (forward and reverse). For generating real sounding nature and weather ambiances. Water, wind, rain, thunder, birds, frogs, farm animals, waves and many more!

7 Generators are at your fingertips for creating amazing ambiances (Generator 1-7). **1 extra Generator** to play solo sounds like birds, dogs, cats, frogs, farm animals, waves, thunderclaps and more (Generator 8).

65+ patches to get you started!



All generators have their own filters, effects, EQ's, LFO's and envelopes.

If you flip the rack over, **17 stereo audio outputs** are revealed. **The main mix, 8 "wet" audio outputs and 8 "dry" audio outputs.** The "wet" audio outputs contain the processed signal of each generator, the "dry" audio outputs contain the signal of the unprocessed/clean signal of each generator. By combining Mixfood Ambi Nature with all your favorite effects that Reason is packed with or combine it with **Mixfood Ambi Urban** endless possibilities are at your fingertips.

How to operate Mixfood Ambi Nature

It's not a regular synth, so the workflow is pretty different.

First of all, **generators 1-7 are all routed to the same keys**. no matter which key you press from C-2 till B2 all play the same note/samples. They play the samples you select in generators 1, 2, 3, 4, 5, 6 and/or 7.




Figure 1 Mixfood Ambi Urban – Keyboard Layout

So, first select the samples you think fit together in generators 1-7 Turn up the volume on each generator (just above 0, if you let the volume sit at 0, the sample will not be loaded).

After you selected the samples and turned up the volume you can just press any key in the range C-2 till B2 to hear the ambiance play. The samples in the selected generators will be played and looped! Create a track, draw in a C2 note and let it play for 15 minutes is the easiest way to edit the ambiance until it is what you want.

Use the mute button to mute the generators you currently don't want to hear so you can finetune the others. The Solo button will only work when you press it down. You can finetune the samples until a perfect ambiance is created.

With the keys C3 and up you can then **play solo samples** as needed. **Each key is mapped to a particular sample**. They are all routed to **generator 8**.

Each generator has an **EDIT button**, when selected the **FX section** will be usable for ONLY THAT PARTICULAR generator with the RED EDIT button on. When you press the main EDIT button, the FX section is applied to the MAIN MIX.




Figure 2 Mixfood Ambi Nature – Edit -> Effects Section




Figure 3 8 Ambiance Generators




Figure 4 8 Sound Shapers & Effects Per Generator




Figure 5 16 Separate Audio Outputs